

Installing TAF 3

To install TAF 3, you need a PC with a Windows operating system. At least Windows 7 is required, we recommend Windows 10. The computer should have 4 GB of RAM and about 500 MB of free disk space.

The installation file can be found at <https://www.lanet2.de> in the Software section. There you can download the demo version.

After downloading, start the installation by double-clicking on the file icon.

After selecting the language for the installation, it will begin. You may be prompted to install Microsoft SQL Server Compact during the installation. If an Internet connection is available, the necessary files will be downloaded and installed automatically.

You may also need to agree to install the "Microsoft Visual C++ 2013 Redistributable" package. After the installation is complete, you can start TAF 3.

If a Windows firewall (or other software firewall) is active, you must allow it not to block TAF - preferably for both private and public networks. If you don't do this, you may have problems later on, when you want to use TAF 3 in the network.

If no license file is installed yet, you have to do this now. To do this, open the item "about TAF" in the help menu and click on "load from file".

Now search for the "program.vrs" file that contains your license.

If the file was read successfully, your license data will be displayed in the window and the program can now be used.